

Hyperemia and Congestion

Active inflow versus passive outflow impairment

Definitions · vascular mechanisms · pulmonary and hepatic morphology

Dr Abu Suraih Sakhri

MBBS, MD (Pathology)

www.abusuraisakhri.com

Learning outcomes

- Differentiate hyperemia from congestion by mechanism and appearance.
- Explain how venous outflow impairment produces edema, hemorrhage, and chronic hypoxic damage.
- Recognize acute and chronic pulmonary and hepatic congestion.
- Connect gross and microscopic findings to their hemodynamic causes.

Blood volume alone does not identify the mechanism

Hyperemia

Increased arterial inflow expands the vascular bed. The process is active.


Congestion

Reduced venous drainage leads to blood accumulation. The process is passive.

The two processes can look red, but their oxygenation and implications differ.

Tissue perfusion depends on inflow and outflow


Blood normally enters and leaves a capillary bed



Balanced delivery and drainage under baseline conditions

Schematic

Hyperemia is an active vascular response



The key initiating event is upstream arteriolar dilation.


Why hyperemic tissue appears red

- Increased flow delivers more oxygenated blood to the affected area.
- Visible erythema reflects the increased oxygenated vascular blood content.
- Color must be interpreted with the vascular mechanism, not in isolation.

Characteristic appearance: Red (erythema)

Arteriolar dilation changes tissue blood flow


Increased inflow with a patent outflow pathway



Arteriolar dilation → increased delivery of oxygenated blood


Schematic

Exercise is a physiologic example of hyperemia



Physiologic hyperemia is a controlled response, not venous stasis.

Inflammation can produce active hyperemia



Hyperemia contributes to redness at inflammatory sites.

Redness is not synonymous with passive congestion

Hyperemic red tissue


Active vessel dilation; Oxygenated blood;
Increased perfusion.

Congested blue-red tissue

Venous backup; Reduced outflow; Greater
deoxygenated hemoglobin.

Histologic and clinical context distinguishes the two.


Congestion begins with impaired venous outflow



Passive congestion results from downstream obstruction or impaired return.

The venous bottleneck

Outflow obstruction with continued inflow




Schematic

Venous congestion may be localized

- A discrete venous obstruction reduces drainage from one affected region.
- The increased venous pressure is geographically limited.
- The same mechanism explains local tissue swelling when hydrostatic pressure rises.

Localized congestion: Isolated venous obstruction

Cardiac failure can cause systemic congestion



The distribution depends on the cardiac failure context and affected vascular beds.

Why congested tissues look blue-red

Venous stasis

Blood remains in local vascular bed



Oxygen extraction continues

Relative deoxygenation of stagnant blood




Deoxyhemoglobin accumulates

Blue-red color predominates

This dusky hue as cyanosis.

Congestion promotes interstitial edema



Edema is a common consequence, not the definition, of congestion.

Edema and congestion describe different compartments

Congestion


Excess blood remains within the vascular compartment because venous outflow is impaired.

Edema

Excess fluid accumulates outside blood vessels in the tissue interstitium.


Elevated hydrostatic pressure links the two.

Prolonged venous congestion causes chronic hypoxia




Severity and duration determine whether structural damage develops.

Capillary rupture introduces blood into tissue



This is focal tissue hemorrhage secondary to congestion.

Hemosiderin records previous erythrocyte leakage



Pigment-laden macrophages are evidence of prior hemorrhage.

Acute versus chronic passive congestion


Feature	Acute	Chronic
Dominant process	Rapid engorgement and edema	Persistent stasis and hypoxic injury
Hemorrhage	Focal extravasation may occur	Repeated red-cell leakage may persist
Tissue response	Predominantly vascular changes	Macrophage pigment and fibrosis may emerge
Typical lesson	Look for engorged vessels	Seek remodeling and hemosiderin

General morphologic hallmarks of congestion

- Grossly: Dusky reddish-blue discoloration from stasis and deoxygenation.
- Microscopically: Engorged blood vessels and region-specific edema or hemorrhage.
- Chronically: Hemosiderin-laden macrophages, tissue loss, and fibrosis may appear.

Interpret morphologic findings in their organ context

The lung is vulnerable to venous back-pressure



Pulmonary morphology changes with duration of congestion.

Acute pulmonary congestion: The triad

Capillary engorgement

Alveolar capillaries are distended by blood.

Septal edema


Fluid accumulates in the alveolar septal interstitium.

Focal hemorrhage

Some erythrocytes leak into alveolar spaces.

Acute lung: Capillary engorgement

Alveolar air spaces




Schematic — not a histology image

Acute congestion

Capillary engorgement; Septal fluid; Focal blood extravasation


Alveolar septal edema follows pressure elevation



The underlying problem is vascular pressure rather than primary epithelial proliferation.

Focal intra-alveolar hemorrhage

Alveolar air spaces




Schematic — not a histology image

Alveolar hemorrhage


Focal erythrocytes enter alveolar spaces

Pulmonary venous congestion can become chronic



Siderophages and fibrotic septa in chronic disease.

Heart failure cells are hemosiderin-laden macrophages




Persistent congestion

Macrophages ingest extravasated erythrocytes; Iron pigment persists


Schematic — not a histology image

Why alveolar macrophages contain iron pigment



The pigment is a record of prior intra-alveolar red-cell leakage.

Chronic congestion thickens alveolar septa



Remodeled septa

Interstitial and alveolar septal fibrosis develops during chronic congestion

Schematic — not a histology image

Chronic pulmonary congestion: Combined morphology

Alveolar septa

Thickened and fibrotic rather than only acutely edematous.


Air spaces

Contain hemosiderin-laden alveolar macrophages.

Microcirculation

Capillary engorgement and past focal hemorrhage underlie findings.

Edema fluid in lung impedes oxygen transfer



The source emphasizes a potentially life-threatening consequence of lung edema.

Pulmonary edema can coexist with pleural effusion

Pulmonary edema

Fluid in lung interstitium and alveolar spaces directly hinders gas exchange.

Pleural effusion

Fluid in pleural space compresses adjacent lung and further impairs gas exchange.

Both can exacerbate respiratory compromise.

Gross pulmonary edema: Fluid and weight

- Pulmonary edema can markedly increase lung weight.
- Sectioning may yield frothy blood-tinged fluid.
- The fluid contains air, edema fluid, and extravasated erythrocytes.

This is source-derived edema context, not a unique sign of congestion

Pulmonary congestion is not equivalent to inflammation

Hydrostatic process


Venous pressure drives noninflammatory fluid movement; Congestion accompanies cardiac dysfunction.

Permeability process

Inflammation increases vascular permeability; Protein-rich exudates can develop.

Different causes may produce alveolar fluid by different mechanisms.

The liver has a downstream vulnerable zone




Schematic — not a histology image

Perfusion gradient


Oxygenated blood enters at portal tracts and traverses sinusoids toward the central vein.

Acute hepatic congestion dilates central drainage



The vascular abnormality is most evident near the central vein.

Zone 3 lies furthest downstream for oxygen delivery




Schematic — not a histology image

Centrilobular vulnerability

The centrilobular region is furthest downstream, making it especially vulnerable to reduced oxygen delivery.

Centrilobular hepatocytes may undergo necrosis



The source describes centrilobular hepatocytes as particularly susceptible.

Periportal hepatocytes may show fatty change


- Periportal hepatocytes lie closer to oxygenated blood entering via hepatic arterioles.
- They may remain better oxygenated than centrilobular hepatocytes.
- The described acute pattern includes periportal fatty change while zone 3 may become necrotic.

Spatial perfusion gradients explain different hepatocyte responses

Acute hepatic congestion: Key contrasts

Region	Vascular setting	Cellular consequence
Central vein	Distended by impaired outflow	Nearby hepatocytes at risk
Centrilobular sinusoids	Marked blood engorgement	Hypoxia; Possible necrosis
Periportal region	Relatively better oxygen supply	May show fatty change

Chronic hepatic congestion creates a mottled liver



Red-brown depressed centers alternate with paler, relatively uncongested parenchyma.

Nutmeg liver: Gross pattern and mechanism

Red-brown centers

Congested, hemorrhagic centrilobular tissue.


Paler surrounding liver

Relatively uncongested tan regions.

Slightly depressed centers


Reflect loss of hepatocytes during chronic injury.

Hepatic congestion leaves microscopic hemorrhage



Together these findings localize chronic vascular injury.

Hepatocyte dropout reflects persistent injury



The degree of loss and necrosis varies.

Chronic hepatic congestion: Microscopic checklist

- Centrilobular sinusoidal congestion and hemorrhage.
- Hemosiderin-laden macrophages in previously hemorrhagic regions.
- Variable hepatocyte dropout and necrosis.
- Gross correlation: Depressed red-brown centrilobular tissue.

Morphology must be assigned to a vascular territory


Acute and chronic liver findings are linked

Acute hepatic congestion	With sustained injury	Chronic hepatic congestion
Central vein distension	Persistent vascular back-pressure	Centrilobular engorgement
Sinusoidal dilation	Tissue hypoxia and leakage	Hemorrhage; Siderophages
Possible zone 3 necrosis	Continued cell loss	Depressed red-brown centers
Relative periportal sparing	Regional color contrast	Nutmeg pattern

Pulmonary and hepatic congestion differ by architecture

Pathologic feature	Lung	Liver
Initial vascular site	Alveolar capillaries	Central veins and sinusoids
Acute extravascular change	Septal edema; Focal hemorrhage	Centrilobular hypoxic injury
Chronic pigment-bearing cells	Heart failure cells in alveoli	Hemosiderin-laden macrophages
Chronic remodeling	Fibrotic alveolar septa	Hepatocyte loss and depressed zones

Venous obstruction raises hydrostatic pressure



This parent-section mechanism links congestion with swelling.

Localized venous obstruction produces regional edema

A patient has a venous obstruction confined to one lower extremity. The tissue is swollen and congested.


Which mechanism best explains the distribution?

A. Localized impaired venous return

B. Generalized loss of plasma albumin

C. Diffuse inflammatory permeability change

The local-edema case: Interpretation




The original chapter uses lower-limb DVT as an example of localized impaired return.

Dependent edema follows gravity

- Elevated hydrostatic pressure can be more apparent in dependent tissue.
- Fluid tends to accumulate in the legs while standing.
- In recumbent patients, sacral tissues may show dependent swelling.

Dependent edema reflects pressure distribution, not a separate vascular disease

Pitting edema reflects mobile interstitial fluid



Pitting edema can accompany systemic or localized hydrostatic disorders.

Transudate and exudate are not interchangeable

Transudate

Usually protein poor; Typical of increased pressure or reduced oncotic pressure.

Exudate

Protein rich; Typically caused by inflammatory increases in vascular permeability.

Edema fluid composition helps distinguish pathophysiologic mechanisms.

An inflammatory focus is not venous congestion

Redness develops in an inflamed tissue region. There is increased local delivery of oxygenated blood.


Which process best accounts for the redness?

A. Active arteriolar hyperemia

B. Passive venous outflow obstruction

C. Long-standing hemosiderin accumulation

The inflammatory redness case: Interpretation



Correct choice: Active arteriolar hyperemia.

Pulmonary case: Identifying chronicity

A lung section from a patient with chronic cardiac failure contains thickened alveolar septa and alveolar macrophages bearing coarse brown pigment.


Which process best explains the pigmented macrophages?

A. Phagocytosis of leaked erythrocytes

B. Acute arteriolar dilation without leakage

C. Periportal hepatocyte fatty change

Pulmonary case: Mechanism of heart failure cells



Septa may also become thickened and fibrotic with chronicity.

Hepatic case: Recognizing nutmeg morphology

A chronically congested liver shows depressed red-brown central regions alternating with relatively tan surrounding tissue.


What best explains the depressed central regions?

A. Centrilobular hepatocyte loss

B. Diffuse arteriolar hyperemia

C. Isolated pleural transudation

Hepatic case: Spatial reasoning



Correct choice: Centrilobular hepatocyte loss.

Integrated comparison: Mechanisms and outcomes

Question	Hyperemia	Congestion
Initiating event	Arteriolar dilation	Reduced venous outflow
Active / passive	Active	Passive
Blood oxygenation appearance	Red oxygenated blood	Dusky blue-red deoxygenated blood
Tissue consequences	Increased flow; Erythema	Edema, hemorrhage, hypoxia, fibrosis
Classic examples	Exercise; Inflammation	Venous obstruction; Cardiac failure

Morphology is a record of time and tissue

Immediate vascular change

Engorged capillaries or sinusoids.

Subsequent extravasation

Edema fluid and erythrocytes enter tissue spaces.

Long-term consequence

Siderophages, cell loss, or fibrosis reveal persistent injury.

Final synthesis: Three diagnostic questions

What drives blood volume?

Increased inflow suggests hyperemia; Impaired outflow suggests congestion.

Where is the fluid or pigment?

Intravascular blood, interstitial edema, or macrophage hemosiderin.

Which organ and duration?

Acute pulmonary triad;
Chronic heart failure cells;
Hepatic nutmeg change.

Primary reference and figure status

Robbins, Cotran & Kumar: Pathologic Basis of Disease

11th edition (2026)

Scientific teaching diagrams are original editable schematics. No genuine microscopic or gross specimen image is reproduced in this deck.