

Morphologic Patterns of Acute Inflammation

Recognizing exudates, surface lesions, and outcomes

Serous fluid

Fibrin

Pus / abscess

Ulceration


Dr Abu Suraih Sakhri

MBBS, MD (Pathology)

www.abusuraihsakhri.com


Morphologic recognition: Learning objectives

- Identify the shared vascular and cellular hallmarks of acute inflammation.
- Distinguish serous, fibrinous, purulent, and ulcerative patterns by their material and architecture.
- Explain how severity, cause, and anatomic site shape the appearance.
- Link each pattern to a characteristic clinical example and potential outcome.




Acute inflammation has a common morphologic substrate

- Dilated small vessels increase blood flow at the injured site.
- Plasma-derived fluid accumulates outside vessels.
- Leukocytes—often initially neutrophils—collect in affected tissues.
- Special patterns add a dominant exudate or a distinctive tissue defect.




Two hallmarks: Vascular dilation and extravasation

- Dilation is a change in intravascular caliber and local perfusion.
- Extravasation moves fluid and leukocytes into interstitial compartments.
- The amount and composition of escaped material influence the appearance.
- Site-specific architecture determines where exudate is visible.




The exudate reflects the local vascular response

- Increased endothelial permeability allows plasma components to leave the circulation.
- Greater permeability can permit large proteins, including fibrinogen, to escape.
- Leukocyte accumulation and cell injury may add cellular debris.
- Classify the dominant pattern rather than assuming one component is exclusive.




Why identical triggers need not look identical

- Intensity of injury influences vascular leakage and tissue destruction.
- Nature of the stimulus influences cellular recruitment and local reactions.
- Tissue architecture determines whether fluid pools, coats a surface, or forms a cavity.
- Host responses and time alter the observed stage of a lesion.



Four major gross and microscopic patterns

- Serous: Predominantly serum-like fluid.
- Fibrinous: Deposited fibrin within tissue or on a serosal surface.
- Purulent: Pus rich in neutrophils and liquefied cellular debris.
- Ulceration: Loss of surface tissue after necrosis and sloughing.



Morphology suggests—but does not prove—etiology

- Serous fluid commonly has few leukocytes and no demonstrable microbes.
- Pyogenic bacteria are frequent triggers of pus formation.
- Fibrin deposition suggests marked vascular leakage plus local coagulation.
- An ulcer identifies superficial necrosis, not one specific cause.

Observe material

Fluid → serous


Fibrin → fibrinous

Pus → suppurative

Surface defect → ulcer

Reading a lesion: Start with the compartment

- Is the dominant abnormality in a body cavity, tissue space, or surface?
- Is there intact overlying epithelium, surface fibrin, or a true crater?
- Are there numerous neutrophils and liquefied necrotic cells?
- Look for concurrent features and evolution over time.




A practical classification matrix

Pattern	Dominant material	Structural clue	Classical example
Serous	Serum-like fluid; Few leukocytes	Blister or serosal effusion	Burn-related skin blister
Fibrinous	Extracellular fibrin	Eosinophilic threads / surface coagulum	Fibrinous pericarditis
Purulent	Neutrophils + liquefied debris	Pus; Localized if abscess	Pyogenic abscess / appendicitis
Ulcer	Sloughed necrotic surface tissue	Loss of epithelium; Crater	Peptic or lower-leg ulcer

Patterns describe predominant morphology; Mixtures and transitions can occur.


Serous inflammation: The defining material

- Serum-like fluid enters tissue spaces created by cell injury.
- Fluid can also accumulate within mesothelium-lined body cavities.
- Large numbers of leukocytes are not the dominant component.
- Serous does not automatically mean a sterile process has been proven.




The fluid-filled space is an anatomic clue

- Skin blister: Fluid accumulates within or immediately below injured epidermis.
- Pericardial, pleural, and peritoneal spaces may contain a serous effusion.
- Histologic emphasis is separation/distension by fluid rather than pus or dense fibrin.




How a skin blister develops

- A burn or certain viral infections injure the epidermal compartment.
- Fluid accumulates inside or beneath the damaged epithelial layer.
- The resulting separation creates a clinically visible blister.
- The schematic depicts a location of fluid—not a particular viral diagnosis.




Serous inflammation in mesothelium-lined cavities

- Pleural, pericardial, and peritoneal spaces can collect fluid.
- The collected fluid is described as an effusion.
- A serosal surface may remain relatively smooth when little fibrin is deposited.
- Fluid location alone cannot determine whether an effusion is inflammatory.




Two possible origins of an inflammatory effusion

- Plasma may escape when local vascular permeability increases.
- Irritated mesothelial cells can contribute fluid to the cavity.
- Either mechanism may occur in a serosal space.
- The term effusion describes location rather than biochemical mechanism.




Cellularity in a typical serous response

- Serous fluid usually lacks large numbers of leukocytes.
- A heavy neutrophilic component would favor a purulent pattern.
- Inflammatory lesions can evolve: Mixed or changing patterns may coexist.
- Interpret fluid morphology with the involved tissue and clinical setting.




Effusion is not synonymous with inflammation

- Inflammatory effusion can reflect vascular permeability or mesothelial irritation.
- Heart failure may yield fluid through altered blood outflow.
- Low plasma protein levels in kidney or liver disease can also yield fluid.
- An effusion therefore requires etiologic interpretation beyond appearance.




Serous versus noninflammatory fluid: Reasoning

- Ask whether the patient has local injury or serosal inflammation.
- Consider circulatory congestion or low plasma oncotic pressure as alternatives.
- Do not infer infection simply from the presence of fluid.
- Laboratory classification requires measurements not specified in this topic.




Serous morphology: What to describe

- Location of the fluid relative to epithelial or serosal layers.
- Degree of separation/distension of the involved compartment.
- Presence or absence of conspicuous neutrophils, fibrin, and necrotic debris.
- Whether the surface remains intact or is already ulcerated.




Clinical example: Burn-related blister

- A raised fluid-filled lesion follows epidermal injury.
- The principal material is a collection of serum-like fluid.
- The fluid does not, by itself, indicate an abscess.
- Morphologic diagnosis: Serous inflammation in a damaged epithelial compartment.




Serous pattern: Reversible injury versus progression

- If damage is limited and the initiating stimulus ends, fluid can be resorbed.
- Macrophages and lymphatic drainage participate in clearing inflammatory material.
- Sustained injury may produce a more cellular exudate or tissue destruction.
- Interpret an isolated image as one point in an evolving process.




Fibrinous inflammation: More than fluid leakage

- Greater permeability permits fibrinogen and other large plasma proteins to escape.
- A local procoagulant stimulus promotes fibrin formation.
- Deposited fibrin becomes the dominant morphologic material.
- Fibrinous exudates are prominent along inflamed serosal surfaces.



From fibrinogen leakage to fibrin deposition

- Vascular permeability increases sufficiently for fibrinogen extravasation.
- Local coagulation turns fibrinogen into insoluble fibrin.
- Threads of fibrin coat a surface or accumulate in extravascular tissue.
- This is a causal sequence, not a quantitative permeability threshold.



Anatomic predilection of fibrinous exudate

- Pericardial and pleural surfaces are important sites.
- Meningeal surfaces can also show a fibrinous exudate.
- Serosa creates an accessible surface on which fibrin deposits are grossly visible.
- Name the involved surface before describing the exudate.


Pericardium

Pleura

Meninges


Gross fibrinous pericarditis: Surface deposition

- Fibrin coats the pericardial surface rather than forming an intraparenchymal abscess.
- Exudate may produce an opaque, roughened surface.
- Compare the smooth normally apposed layers with fibrin-bearing layers.
- Dense deposition may later lead to fibrous thickening.




Fibrin on microscopy: Eosinophilic threads

- Fibrin often forms an eosinophilic meshwork on H&E sections.
- It may alternatively appear as an amorphous eosinophilic coagulum.
- Identify the serosal tissue beneath the deposited material.
- The diagram is schematic; Actual photomicrograph interpretation requires a specimen.




Why fibrin may appear amorphous

- Fibrin can aggregate into a relatively homogeneous-appearing surface layer.
- Its thread-like quality varies with section orientation and density.
- Both meshwork and amorphous coagulum are recognized textbook patterns.
- The key observation remains extracellular fibrin deposition.




Fibrinous exudate can be removed

- Fibrinolysis may dissolve deposited fibrin.
- Macrophages can clear the resulting material.
- A successfully cleared exudate need not leave a permanent scar.
- Complete removal is more likely when persistent injury is controlled.



Failure of fibrin clearance leads to organization


- Persistent fibrin provides a substrate for tissue ingrowth.
- Fibroblasts and new blood vessels invade the exudate.
- Connective tissue replaces the original fibrin deposit.
- The name for this replacement process is organization.



Organized pericardial exudate changes anatomy


- Fibrous tissue may thicken pericardial and epicardial surfaces.
- Extensive organization can obliterate the pericardial space.
- Loss of the normal serosal plane is a structural consequence of persistent exudate.
- Do not infer functional severity solely from a schematic.

Original schematic · not a specimen




Clearance or fibrosis: The two trajectories of fibrin

- Removal: Fibrinolysis plus macrophage clearance.
- Organization: Fibroblast and vascular ingrowth.
- The balance depends on persistence and clearance of the injury/exudate.
- Organization is not identical to ongoing fibrin deposition.




Distinguish fibrinous from serous inflammation

- Serous: Conspicuous fluid with relatively sparse cells.
- Fibrinous: Conspicuous eosinophilic strands or surface coagulum.
- Fibrin requires large protein leakage plus a coagulation-promoting environment.
- Mixed serofibrinous appearances may occur in real tissue.



Interpretation exercise: An opaque pericardial coat


- Observed: A roughened serosal surface with an adherent fibrin-rich exudate.
- Pattern: Fibrinous inflammation.
- Outcome to watch: Clearance versus fibrous organization.
- Pattern recognition cannot establish a unique etiology.



Purulent inflammation is defined by pus

- Pus is an exudate containing neutrophils, liquefied cellular debris, and edema fluid.
- Localized tissue destruction gives the fluid a turbid or creamy appearance.
- The pattern is also termed suppurative inflammation.
- Its common cause is infection by pyogenic bacteria.

Original schematic · not a specimen




Neutrophils + liquefied necrotic material

The constituents of pus have different origins

- Neutrophils arrive through inflammatory leukocyte recruitment.
- Necrotic tissue cells and leukocytes contribute cellular debris.
- Edema fluid supplies the liquid phase.
- Microbial organisms may be present depending on the cause and sampling.

Original schematic · not a specimen



Neutrophils + liquefied necrotic material

Why pyogenic infections produce suppuration

- Certain bacteria provoke marked neutrophilic responses.
- Tissue digestion and neutrophil breakdown contribute to liquefactive necrosis.
- Staphylococci are a textbook example of pyogenic bacteria.
- Purulent morphology strongly suggests, but does not independently prove, a bacterial cause.

Pyogenic stimulus


Neutrophils recruited

Liquefactive necrosis

Pus formation

Neutrophil-rich inflammation versus true pus


- Acute inflammation can recruit neutrophils before pus develops.
- Pus additionally contains liquefied tissue and leukocyte debris.
- A dense cellular infiltrate alone is not identical to an abscess cavity.
- Architecture and necrosis must be assessed together.



Acute appendicitis as a suppurative example

- Acute appendicitis as a common example of suppurative inflammation.
- The dominant acute cellular population is neutrophilic.
- Use tissue context rather than gross color alone to classify the response.
- Appendicitis is an example—not a morphologic definition of all purulence.


Original schematic · not a specimen



Neutrophils + liquefied necrotic material


Abscess: Pus localized in a confined focus

- An abscess is a circumscribed collection of pus.
- It may form in tissue, within an organ, or in a confined space.
- Pyogenic bacterial seeding is an important mechanism.
- The architecture distinguishes an abscess from diffuse suppuration.




Abscess architecture has recognizable zones

- Center: Liquefied necrotic leukocytes and tissue cells.
- Inner surrounding zone: More preserved neutrophils.
- Outer zone: Dilated vessels and tissue response.
- Chronic inflammation and repair may develop beyond the acute focus.




The center of an abscess is liquefied tissue

- Tissue architecture is lost within the necrotic center.
- Necrotic neutrophils mix with destroyed parenchymal cells.
- Fluid-rich debris forms the abscess core.
- Distinguish this focus from intact, viable tissue at the periphery.



The abscess rim shows host containment

- Neutrophils persist around the central necrotic compartment.
- Adjacent small vessels may be markedly dilated.
- Outside the rim, proliferating stromal cells and vessels signal repair.
- The spatial pattern helps establish lesion age and response.



Evolution: Abscess walling-off and fibrosis

- The acute purulent focus may become increasingly circumscribed.
- Fibroblastic proliferation can form a more distinct peripheral wall.
- Over time, connective tissue may replace the focus.
- Persistent infection can prevent timely resolution.

Bacterial seeding

Purulent focus

Walling-off


Fibrous replacement

Abscess versus diffuse purulent inflammation


- Abscess: A localized necrotic fluid collection in a defined compartment.
- Diffuse suppuration: Neutrophilic exudate spread through a tissue or surface.
- Both may be caused by pyogenic bacteria.
- Localization is an anatomic observation, not a separate microbial species.

Original schematic · not a specimen

Confined abscess




Diffuse suppuration




Do not confuse fibrin with purulent debris

- Fibrin: Mainly deposited extracellular protein with thread-like/coagulated texture.
- Pus: Mainly neutrophils, necrotic cells, and edema fluid.
- Fibrin and neutrophils can coexist in mixed inflammatory exudates.
- Describe the dominant material and the tissue damage.




Clinical scenario: A focal lung collection

- Gross finding: A discrete cavity filled with thick inflammatory material.
- Histologic concept: Liquefaction centrally and neutrophils around it.
- Morphologic designation: Pulmonary abscess.
- Morphology establishes a suppurative pattern, not the responsible organism.




Ulcer: A defect created by tissue loss

- Ulceration is focal loss or excavation of an organ or tissue surface.
- Inflamed necrotic tissue sloughs, leaving a surface defect.
- Ulceration therefore requires necrosis at or near a surface.
- Its hallmark is tissue absence—not a particular type of exudate.



Surface location is essential for ulceration

- A mucosal or cutaneous epithelial boundary is a typical site.
- Destruction beneath an intact surface may instead produce an internal focus.
- When surface tissue detaches, a visible excavation remains.
- The underlying inflammatory response may be acute, chronic, or mixed.



From surface injury to an ulcer crater

- Surface epithelium becomes injured and necrotic.
- Damaged tissue is shed from the surface.
- A depressed crater exposes inflamed underlying tissue.
- Sustained injury recruits additional inflammatory cells and repair reactions.

Surface necrosis

Sloughing

Tissue crater

Repair / chronicity

Common mucosal sites of ulceration

- Mouth, stomach, intestines, and genitourinary tract are recognized sites.
- Peptic ulcers in the stomach or duodenum are classic examples.
- Describe the involved epithelial compartment and defect depth.
- The same term “ulcer” does not specify the primary disease.

Mouth / GI mucosa

Genitourinary mucosa

Skin

Lower-extremity ulcers: Vascular susceptibility

- Skin and subcutaneous tissues of the lower extremity are frequent sites.
- Vascular insufficiency predisposes tissue to damage and impaired repair.
- Diabetes, sickle cell anemia, and peripheral vascular disease.
- Risk factors are not interchangeable with a histologic diagnosis.

Reduced tissue perfusion


Peripheral vascular disease

Diabetes-related vulnerability

Sickle cell disease


Acute ulcer margin: Active tissue injury

- Neutrophils accumulate at the margins and surface.
- Vascular dilation contributes to hyperemia around the defect.
- Necrotic debris may be present in the crater.
- Acute inflammation is most prominent in actively injured regions.




Chronic ulcer base: Repair coexists with injury

- Fibroblasts proliferate as a repair response.
- Collagenous scar develops within the base and edges.
- Lymphocytes, macrophages, and plasma cells can accompany chronicity.
- Active neutrophils and chronic reparative tissue may occur together.




Peptic ulcer as an acute–chronic interface

- Gastric or duodenal peptic ulceration to demonstrate mixed inflammation.
- The crater records surface necrosis and sloughing.
- An acutely inflamed region may overlies more chronic fibrosis and cells.
- The pattern is an excavation with superimposed inflammatory layers.




Ulceration versus abscess: The discriminant

- Ulcer: Surface loss and excavation following necrosis.
- Abscess: A localized collection of liquefied necrotic tissue and pus.
- An ulcer may develop secondary purulent exudate at its base.
- One lesion may display features of both, but their definitions remain distinct.




Describe an ulcer with tissue-based language

- Identify location: Skin or specific mucosa.
- Identify the defect: Surface loss, exposed base, and margins.
- Describe inflammatory components: Neutrophils versus mononuclear cells.
- Assess the reparative component: Fibroblasts and scar tissue.



Clinical scenario: A chronic duodenal crater

- A mucosal defect has acute neutrophilic exudate at its exposed base.
- Fibrosis and chronic inflammatory cells occur deeper and at the margins.
- The lesion is an ulcer with concurrent acute and chronic inflammation.
- The morphological description does not establish its specific upstream cause.



Read four patterns by the dominant observation

Pattern	Dominant material	Structural clue	Classical example
Serous	Serum-like fluid; Few leukocytes	Blister or serosal effusion	Burn-related skin blister
Fibrinous	Extracellular fibrin	Eosinophilic threads / surface coagulum	Fibrinous pericarditis
Purulent	Neutrophils + liquefied debris	Pus; Localized if abscess	Pyogenic abscess / appendicitis
Ulcer	Sloughed necrotic surface tissue	Loss of epithelium; Crater	Peptic or lower-leg ulcer

Patterns describe predominant morphology; Mixtures and transitions can occur.

A single specimen can show overlapping patterns

- Serous fluid may coexist with fibrin deposition.
- Fibrin and neutrophilic exudate may coexist on an inflamed surface.
- An ulcer base may contain neutrophils, debris, and scar.
- Use precise descriptive terms and identify the dominant process.

One specimen

Fluid + fibrin

Fibrin + neutrophils

Ulcer + necrotic debris

Chronic repair + acute cells

Three major outcomes of acute inflammation

- Resolution restores tissue when injury is limited and cells can regenerate.
- Fibrosis follows major destruction, impaired regeneration, or unremoved fibrin.
- Chronic inflammation may follow persistence of the injurious stimulus.
- Clinical and anatomic context helps predict which pathway is likely.

Limited injury → resolution

Major damage → fibrosis

Persistent stimulus → chronicity

Outcome follows the material that must be cleared

- Fluid: Resorption and drainage can restore an undamaged compartment.
- Fibrin: Fibrinolysis/macrophage clearance or fibrous organization.
- Pus: Removal of the trigger plus clearance of necrotic material; Possible scarring.
- Ulcer: Repair may produce fibrosis, especially with persistent tissue injury.

Fluid → drainage





Fibrin → clear / organize

Pus → clear / scar

Ulcer → heal / scar

Case comparison: Assign the correct pattern

- A burn produces fluid beneath the epidermis → serous.
- A pericardial surface is coated by eosinophilic threads → fibrinous.
- A focal cavity contains neutrophils and liquefied cell debris → abscess.
- A duodenal mucosal crater has an inflamed base → ulcer.



Common interpretive pitfalls

- An effusion is not always inflammatory.
- Neutrophils are not sufficient to establish an abscess.
- Fibrin deposition does not guarantee subsequent fibrosis.
- An ulcer is defined by surface tissue loss, not by the presence of pus.

Effusion

Not always inflammation

Neutrophils

Not automatically an abscess

Fibrin


Not always persistent scar

Crater

Defines an ulcer





Diagnostic integration: Lesion, material, outcome

- First locate the lesion relative to a surface, cavity, and surrounding tissue.
- Then identify the dominant fluid, extracellular protein, cells, or missing tissue.
- Next determine whether necrosis and repair are present.
- Finally offer a pattern-based diagnosis with appropriate etiologic caution.



Morphologic patterns: Synthesis

- Serous = serum-like fluid in a newly created space or mesothelial cavity.
- Fibrinous = fibrinogen escape, local coagulation, and fibrin deposition.
- Purulent = neutrophils with liquefied necrotic debris; Abscess if localized.
- Ulcer = sloughed necrotic surface tissue with an epithelial defect.



References

- Robbins, Cotran & Kumar: Pathologic Basis of Disease. 11th edition (2026), Chapter 3: Inflammation and Repair.
- Included sections: morphologic patterns; serous, fibrinous and purulent inflammation; abscesses; ulcers; outcomes of acute inflammation.